

Lab cấu hình cơ bản firewall asa


Chuẩn bị

- Một Firewall asa
- Một máy window đặt ip tĩnh 192.168.1.2
- Một máy linux đặt ip tĩnh 172.16.0.1

Mục tiêu

- Khảo sát các chế độ dòng lệnh trên Firewall ASA.
- Thực hành đặt tên(hostname) cho asa.
- Cấu hình IP trên các interface của Firewall ASA.
- Cấu hình cho phép ICMP từ vùng Inside tới vùng DMZ.
- Cấu hình cấp DHCP vùng Inside.
- Cấu hình NAT overload.
- Cấu hình NAT Overload trên Firewall ASA cho phép các PC thuộc Inside Zone truy cập được
- Lưu lại cấu hình trên Firewall ASA.

Mô hình




Mô tả: Mô hình gồm 1 firewall kết nối với internet qua cổng Gi0/1, vùng DMZ có subnet là 172.16.0.0/24 chứa một máy linux, Vùng client là vùng có subnet 192.168.1.0/24 gồm 1 switch và 1 máy window.

Phần thực hành

1. Thực hành khảo sát các chế độ dòng lệnh trên Firewall ASA

Bên dưới là các chế độ dòng lệnh trên asa.



Khi khởi động lên asa sẽ ở chế độ EXEC Mode

```
ASAav
INFO: Power-On Self-Test in process.
.....
INFO: Power-On Self-Test complete.

On virtual platforms the SW-DRBG health test will be run twice:
INFO: Starting SW-DRBG health test...
INFO: SW-DRBG health test passed.

INFO: Starting SW-DRBG health test...
INFO: SW-DRBG health test passed.
Creating trustpoint " SmartCallHome_ServerCA" and installing certificate...
% CA Cert not yet valid or is expired -
  start date: 00:00:00 UTC Oct 31 2013
  end   date: 23:59:59 UTC Oct 30 2023
User enable_1 logged in to ciscoasa
Logins over the last 1 days: 1.
Failed logins since the last login: 0.
Type help or '?' for a list of available commands.
ciscoasa>
Warning: ASAav platform license state is Unlicensed.
Install ASAav platform license for full functionality.
ciscoasa>
```

Để vào chế độ Privileged EXEC Mode dùng lệnh

```
ciscoasa> enable
```

Password: # Nhấn enter khi chưa đặt mật khẩu

```
ASAv
INFO: converting 'fixup protocol sip udp 5060' to MPF commands
INFO: converting 'fixup protocol xdmcp 177' to MPF commands

INFO: Power-On Self-Test in process.
.....
INFO: Power-On Self-Test complete.

On virtual platforms the SW-DRBG health test will be run twice:
INFO: Starting SW-DRBG health test...
INFO: SW-DRBG health test passed.

INFO: Starting SW-DRBG health test...
INFO: SW-DRBG health test passed.
Creating trustpoint "_SmartCallHome_ServerCA" and installing certificate...
% CA Cert not yet valid or is expired -
  start date: 00:00:00 UTC Oct 31 2013
  end  date: 23:59:59 UTC Oct 30 2023
User enable_1 logged in to ciscoasa
Logins over the last 1 days: 1.
Failed logins since the last login: 0.
Type help or '?' for a list of available commands.
ciscoasa> enable
Password:
ciscoasa#
```

Để vào chế độ Global Configuration Mode dùng lệnh

```
ciscoasa# configure terminal
```

```
ASAv
  end  date: 23:59:59 UTC Oct 30 2023
User enable_1 logged in to ciscoasa
Logins over the last 1 days: 1.
Failed logins since the last login: 0.
Type help or '?' for a list of available commands.
ciscoasa> enable
Password:
ciscoasa#
Warning: ASAv platform license state is Unlicensed.
Install ASAv platform license for full functionality.

ciscoasa# configure terminal
ciscoasa(config)#
```

Để trở về chế độ trước đó sử dụng lệnh

```
ciscoasa(config)# exit
```

```
ciscoasa#exit
```

```
ASAv
Please remember to save your configuration.


ciscoasa(config)# Password:
^
ERROR: % Invalid input detected at '^' marker.
ciscoasa(config)# ciscoasa#
^
ERROR: % Invalid input detected at '^' marker.
ciscoasa(config)#
ciscoasa(config)#
ciscoasa(config)#
ciscoasa(config)# exit
ciscoasa# exit

Logoff

User enable_1 logged in to ciscoasa
Logins over the last 1 days: 2. Last login: 09:19:48 UTC Jul 11 2025 from conse
Failed logins since the last login: 0.
Type help or '?' for a list of available commands.
```

2. Thực hành đặt tên(hostname) cho asa.

```
ciscoasa> en
Password:
ciscoasa# conf t
ciscoasa(config)# hostname asa
```




```
ASAv
ERROR: % Invalid input detected at '^' marker.
ciscoasa(config)# ciscoasa#
ERROR: % Invalid input detected at '^' marker.
ciscoasa(config)#
ciscoasa(config)#
ciscoasa(config)# exit
ciscoasa# exit

Logoff

User enable_1 logged in to ciscoasa
Logins over the last 1 days: 2. Last login: 09:19:48 UTC Jul 11 2025 from conse
Failed logins since the last login: 0.
Type help or '?' for a list of available commands.
ciscoasa> ciscoasa(config)# exit
ERROR: % Invalid input detected at '^' marker.
ciscoasa> en
Password:
ciscoasa# conf t
ciscoasa(config)# hostname asa
asa(config)#
```

3. Cấu hình password cho ASA

```
asa# conf t
asa(config)# enable password VnPro@123
asa(config)# exit
asa# exit
```




```
asa# conf t
asa(config)# enable password VnPro@123
asa(config)# ex
asa# ex

Logoff

User enable_1 logged in to asa
Logins over the last 1 days: 4. Last login: 10:46:30 UTC Jul 11 2025 from conse
Failed logins since the last login: 0.
Type help or '?' for a list of available commands.
```

Kiểm tra lại bằng cách exit ra Privileged EXEC Mode, sau đó vào enable, nhập mật khẩu.



```
asa> en
Password:
Invalid password
Password: *****
asa#
```

4. Cấu hình IP trên các interface của Firewall ASA.


Để xem thông tin interface dùng lệnh

```
asa# show interface ip brief
```

```
asa(config)# show interface ip brief
Interface          IP-Address      OK? Method Status      Prol
GigabitEthernet0/0 unassigned      YES unset   administratively down up
GigabitEthernet0/1 unassigned      YES unset   administratively down up
GigabitEthernet0/2 unassigned      YES unset   administratively down up
GigabitEthernet0/3 unassigned      YES unset   administratively down up
GigabitEthernet0/4 unassigned      YES unset   administratively down up
GigabitEthernet0/5 unassigned      YES unset   administratively down up
GigabitEthernet0/6 unassigned      YES unset   administratively down up
Management0/0     unassigned      YES unset   administratively down up
```

Cấu hình ip trên interface gigabitEthernet0/2

```
asa(config)# interface g0/2 # truy cập interface
asa(config-if)# security-level 100 # gán mức độ security
asa(config-if)# nameif Inside #đặt tên cho interface
asa(config-if)# ip address 192.168.1.1 255.255.255.0 #gán địa chỉ ip
asa(config-if)# no shut
asa(config-if)# exit
```



```
ASA
ERROR: % Invalid input detected at '^' marker.
asa# show interface ip brief
Interface          IP-Address      OK? Method Status      Prol
GigabitEthernet0/0 unassigned      YES unset   administratively down up
GigabitEthernet0/1 10.215.27.53    YES DHCP    up
GigabitEthernet0/2 unassigned      YES unset   administratively down up
GigabitEthernet0/3 unassigned      YES unset   administratively down up
GigabitEthernet0/4 unassigned      YES unset   administratively down up
GigabitEthernet0/5 unassigned      YES unset   administratively down up
GigabitEthernet0/6 unassigned      YES unset   administratively down up
Management0/0     unassigned      YES unset   administratively down up
asa#
Warning: ASAv platform license state is Unlicensed.
Install ASAv platform license for full functionality.

asa# conf t
asa(config)# interface g0/2
asa(config-if)# security-level 100
asa(config-if)# nameif Inside
asa(config-if)# ip address 192.168.1.1 255.255.255.0
asa(config-if)# no shut
asa(config-if)# exit
```

Làm tương tự với interface g0/3

```
asa(config)# interface g0/3
asa(config-if)# ip address 172.16.0.1 255.255.255.0
asa(config-if)# security-level 50
asa(config-if)# nameif DMZ
asa(config-if)# no shut
asa(config-if)# exit
```

```
ASAv
^
ERROR: % Invalid input detected at '^' marker.
asa(config)# asa(config-if)# nameif Inside
^
ERROR: % Invalid input detected at '^' marker.
asa(config)# asa(config-if)# ip address 192.168.1.1 255.255.255.0
^
ERROR: % Invalid input detected at '^' marker.
asa(config)# asa(config-if)# no shut
^
ERROR: % Invalid input detected at '^' marker.
asa(config)# asa(config-if)# exit
^
ERROR: % Invalid input detected at '^' marker.
asa(config)# asa(config)#
^
ERROR: % Invalid input detected at '^' marker.
asa(config)# interface g0/3
asa(config-if)# ip address 172.16.0.1 255.255.255.0
asa(config-if)# security-level 50
asa(config-if)# nameif DMZ
asa(config-if)# no shut
asa(config-if)# exit
asa(config-if)# exit
asa(config)#
```

Kiểm tra lại kết quả sau khi cấu hình:

```
asa# show interface ip brief
```


```
ASAv
asa(config)# exit
asa# show int ip brief
Interface          IP-Address      OK? Method Status        Prol
GigabitEthernet0/0 unassigned      YES unset  administratively down up
GigabitEthernet0/1 10.215.27.53   YES DHCP    up            up
GigabitEthernet0/2 192.168.1.1    YES manual  up            up
GigabitEthernet0/3 172.16.0.1     YES manual  up            up
GigabitEthernet0/4 unassigned      YES unset  administratively down up
GigabitEthernet0/5 unassigned      YES unset  administratively down up
GigabitEthernet0/6 unassigned      YES unset  administratively down up
Management0/0     unassigned      YES unset  administratively down up
```

Kiểm tra nameif và security-level

```
asa# show nameif
```

```
asa# show nameif
Interface          Name             Security
GigabitEthernet0/1 Outside          0
GigabitEthernet0/2 Inside           100
GigabitEthernet0/3 DMZ              50
asa#
```

Kiểm tra kết nối trên các thiết bị đầu cuối window



```


C:\Windows\system32>ping 192.168.1.1

Pinging 192.168.1.1 with 32 bytes of data:
Reply from 192.168.1.1: bytes=32 time=12ms TTL=255
Reply from 192.168.1.1: bytes=32 time=5ms TTL=255
Reply from 192.168.1.1: bytes=32 time=4ms TTL=255
Reply from 192.168.1.1: bytes=32 time=7ms TTL=255

Ping statistics for 192.168.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 4ms, Maximum = 12ms, Average = 7ms

C:\Windows\system32>
C:\Windows\system32>
C:\Windows\system32>
C:\Windows\system32>
  
```

Kiểm tra trên thiết bị đầu cuối ubuntu



```

root@vnpro: ~
64 bytes from 172.16.0.1: icmp_seq=1 ttl=255 time=8.79 ms
64 bytes from 172.16.0.1: icmp_seq=2 ttl=255 time=1.61 ms

--- 172.16.0.1 ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 1001ms
rtt min/avg/max/mdev = 1.611/5.200/8.790/3.589 ms
^Croot@vnpro:~# ping 172.16.0.1
PING 172.16.0.1 (172.16.0.1) 56(84) bytes of data:
64 bytes from 172.16.0.1: icmp_seq=1 ttl=255 time=7.10 ms
64 bytes from 172.16.0.1: icmp_seq=2 ttl=255 time=1.55 ms
64 bytes from 172.16.0.1: icmp_seq=3 ttl=255 time=1.72 ms
64 bytes from 172.16.0.1: icmp_seq=4 ttl=255 time=2.80 ms
64 bytes from 172.16.0.1: icmp_seq=5 ttl=255 time=1.64 ms
64 bytes from 172.16.0.1: icmp_seq=6 ttl=255 time=1.55 ms
64 bytes from 172.16.0.1: icmp_seq=7 ttl=255 time=1.61 ms
64 bytes from 172.16.0.1: icmp_seq=8 ttl=255 time=1.95 ms
^C
--- 172.16.0.1 ping statistics ---
8 packets transmitted, 8 received, 0% packet loss, time 7012ms
rtt min/avg/max/mdev = 1.552/2.489/7.096/1.783 ms
root@vnpro:~#
root@vnpro:~#
root@vnpro:~#
root@vnpro:~#
  
```

5. Cấu hình cho phép ICMP từ vùng Inside tới vùng DMZ.

```

asa(config)# class-map inspection_default
asa(config-cmap)# match default-inspection-traffic
asa(config-cmap)# exit
asa(config)# policy-map global_policy
asa(config-pmap)# class inspection_default
asa(config-pmap-c)# inspect icmp
asa(config-pmap-c)# exit
asa(config-pmap)# exit
asa(config)# service-policy global_policy global
  
```

```
ASAv
asa(config)# class-map inspection_default
asa(config-cmap)# match default-inspection-traffic
asa(config-cmap)# exit
asa(config)# policy-map global_policy
asa(config-pmap)# class inspection_default
asa(config-pmap-c)# inspect icmp
asa(config-pmap-c)# exit
asa(config-pmap)# exit
asa(config)# service-policy global_policy global
WARNING: Policy map global_policy is already configured as a service policy
asa(config)#
```

Kiểm tra kết quả:

Trên máy window ping được vùng DMZ

```
C:\Windows\system32>ping 172.16.0.2

Pinging 172.16.0.2 with 32 bytes of data:
Reply from 172.16.0.2: bytes=32 time=15ms TTL=64
Reply from 172.16.0.2: bytes=32 time=9ms TTL=64
Reply from 172.16.0.2: bytes=32 time=12ms TTL=64
Reply from 172.16.0.2: bytes=32 time=7ms TTL=64

Ping statistics for 172.16.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 7ms, Maximum = 15ms, Average = 10ms


C:\Windows\system32>
```

6. Cấu hình cấp DHCP vùng Inside.

```
asa(config)# dhcpd address 192.168.1.2-192.168.1.254 Inside
asa(config)# dhcpd option 3 ip 192.168.1.1 interface Inside
asa(config)# dhcpd option 6 ip 8.8.8.8 interface Inside
asa(config)# dhcpd enable Inside
```

```
asa(config)# dhcpd add
asa(config)# dhcpd address 192.168.1.2-192.168.1.254 Inside
asa(config)# dhcpd option 3 ip 192.168.1.1 interface Inside
asa(config)# dhcpd option 6 ip 8.8.8.8 interface Inside
asa(config)# dhcpd enable Inside
asa(config)#
```

Kiểm tra kết quả, trên máy Window đổi thành ip DHCP.



Sau đó dùng lệnh `ipconfig /renew`

```
C:\Windows\system32>ipconfig /renew

Windows IP Configuration

Ethernet adapter Ethernet:

    Connection-specific DNS Suffix  . : 
    Link-local IPv6 Address . . . . . : fe80::39d5:3298:54cd:4f8e%8
    IPv4 Address. . . . . : 192.168.1.2
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.1.1

C:\Windows\system32>
```

7. Nhận DHCP từ vùng Outside.

```
asa(config)# int g0/1
asa(config-if)# nameif Outside
INFO: Security level for "Outside" set to 0 by default.
asa(config-if)# security-level 0
asa(config-if)# ip address dhcp setroute
asa(config-if)# no shut
```

```
asa(config)# int g0/1
asa(config-if)# nameif Outside
INFO: Security level for "Outside" set to 0 by default.
asa(config-if)# security-level 0
asa(config-if)# ip address dhcp setroute
asa(config-if)# no shut
asa(config-if)#
asa(config-if)#
asa(config-if)# do show ip int brief
```

Kiểm tra lại bằng lệnh

```
show ip address outside dhcp lease
```

```
asa# show ip address outside dhcp lease
Temp IP addr: 10.215.27.53 for peer on Interface: Outside
Temp subnet mask: 255.255.254.0
DHCP Lease server: 10.215.26.9, state: 3 Bound
DHCP transaction id: 0x9715577
Lease: 7200 secs, Renewal: 3600 secs, Rebind: 6300 secs
Temp default-gateway addr: 10.215.26.9
Next timer fires after: 226 seconds
Retry count: 0 Client-ID: cisco-5010.0001.0002-Outside-asa
Proxy: FALSE
Hostname: asa
asa#
```

Lúc này firewall đã có thể ping được ra internet

```
asa# ping 8.8.8.8
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 8.8.8.8, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 60/64/70 ms
asa#
```

8. Cấu hình NAT overload.

```
asa(config)# object network Inside.Zone
asa(config-network-object)# subnet 192.168.1.0 255.255.255.0
asa(config-network-object)# nat (Inside,Outside) dynamic interface
asa(config-network-object)# exit
```

```
asa# conf t
asa(config)# object network Inside.Zone
asa(config-network-object)# subnet 192.168.1.0 255.255.255.0
asa(config-network-object)# nat (Inside,Outside) dynamic interface
asa(config-network-object)# exit
asa(config)#
```

Kiểm tra lại bằng cách ping đến 8.8.8.8 trên máy window.

```
Select Administrator: C:\Windows\System32\cmd.exe
C:\Windows\system32>ping 8.8.8.8

Pinging 8.8.8.8 with 32 bytes of data:
Reply from 8.8.8.8: bytes=32 time=69ms TTL=112
Reply from 8.8.8.8: bytes=32 time=66ms TTL=112
Reply from 8.8.8.8: bytes=32 time=64ms TTL=112
Reply from 8.8.8.8: bytes=32 time=67ms TTL=112

Ping statistics for 8.8.8.8:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 64ms, Maximum = 69ms, Average = 66ms

C:\Windows\system32>
```

9. Lưu lại cấu hình

```
asa# write memory
```

```
ASAv
asa# write memory
Building configuration...
Cryptochecksum: d9936ff5 0c6cc711 051f1716 7dcbc3e5

3925 bytes copied in 0.360 secs
[OK]
asa# show startup-config
: Saved
:
: Serial Number: 9AXMEAWAW6A
: Hardware:  ASAv, 2048 MB RAM, CPU Xeon E5 series 2199 MHz
: Written by enable_15 at 10:51:13.009 UTC Fri Jul 11 2025
```

Như vậy toàn bộ cấu hình sẽ được lưu, trong trường hợp shutdown hay reload đều giữ nguyên cấu hình.